

Configuring MPLS Label Imposition

This chapter contains information on how to configure multiprotocol label switching (MPLS) label imposition.

- About MPLS Label Imposition, on page 1
- Guidelines and Limitations for MPLS Label Imposition, on page 2
- Configuring MPLS Label Imposition, on page 2
- Verifying the MPLS Label Imposition Configuration, on page 6
- Configuration Examples for MPLS Label Imposition, on page 8

About MPLS Label Imposition

An outgoing label stack having one or more labels can be statically provisioned using the MPLS Label Stack Imposition feature. The outgoing label stack is used in the following two types of statically configured MPLS bindings:

- Prefix and Label to Label Stack - Here an IP prefix or an incoming label is mapped to an outgoing stack, similar to static MPLS. An incoming prefix is mapped to out-label-stack for IP-only ingress traffic.
- Label to Label Stack - Here only an incoming label is mapped to an outgoing stack without any prefix.

The new MPLS binding types are implemented in the static MPLS component and are available only when the **feature mpls segment-routing** command is enabled.

If configured next-hops of MPLS label imposition are SR recursive next-hops (RNH), then they are resolved to actual next-hops using RIB. The outer label of the out-label stack is imposed automatically from the SR allocated labels.

ECMP is also supported by adding a number of path configurations.

Note The static MPLS process is started when either the **feature mpls segment-routing** command or the **feature mpls static** command is run. Certain standard static MPLS commands will not be available when static MPLS is run using the **feature mpls segment-routing** command, and the commands for MPLS bindings will not be available when the **feature mpls static** command is run.

Guidelines and Limitations for MPLS Label Imposition

MPLS label imposition has the following guidelines and limitations:

- MPLS label imposition is supported for the following:
  - Cisco Nexus 9200, 9300, 9300-EX, 9300-FX and 9500 platform switches with the 9400, 9500, 9600, and 9700-FX line cards.
  - Cisco Nexus 3164Q, 31128PQ, 3232C, and 3264Q switches.
  - Beginning with Cisco NX-OS Release 9.2(1) release, it is supported on Cisco Nexus 9364C Switch.
  - Beginning with Cisco NX-OS Release 9.3(3), it is supported on Cisco Nexus 9364C-GX, 9316D-GX, and 93600CD-GX switches.
- MPLS label imposition supports only IPv4.
- The maximum number of labels in an out-label stack is five for Cisco Nexus 9200, 9300-EX, and 9300-FX platform switches and three for Cisco Nexus 9300 and 9500 platform switches and Cisco Nexus 3164Q, 31128PQ, 3232C, and 3264Q switches. If you try to impose more labels, the trailing label is truncated automatically, and a syslog error message appears signaling to correct the configuration.
- Multicast is not supported for MPLS label imposition.
- In the multi-label stack configuration, changing an outgoing path is allowed only for Cisco Nexus 9200 and 9300-EX Series switches.
- Subinterfaces and port channels are not supported for MPLS label imposition.
- Prefixes and associated subnet masks learned from routing protocols (including from static routes) cannot be used as part of the label stack imposition policy.
- For label stack imposition verified scalability limits, see the Verified Scalability Guide for your device.

Configuring MPLS Label Imposition

Enabling MPLS Label Imposition

You must install and enable the MPLS feature set and then enable the MPLS segment routing feature before you can configure MPLS label imposition.

Procedure

	Command or Action	Purpose

Step 1	**configure terminal**
	Example:
	`switch# configure terminal`
	`switch(config)#`
		Enters global configuration mode.

	Command or Action	Purpose
Step 2	[**no**] **install feature-set mpls** **Example:** `switch(config)# install feature-set mpls`	Installs the MPLS feature set. The **no** form of this command uninstalls the MPLS feature set.
Step 3	[**no**] **feature-set mpls** **Example:** `switch(config)# feature-set mpls`	Enables the MPLS feature set. The **no** form of this command disables the MPLS feature set.
Step 4	[**no**] **feature mpls segment-routing** **Example:** `switch(config)# feature mpls segment-routing`	Enables the MPLS segment routing feature. The **no** form of this command disables the MPLS segment routing feature.

Step 5	(Optional) **show feature-set**
	Example:
	`switch(config)# show feature-set`
	`Feature Set Name ID State`
	`-------------------- -------- --------`
	`mpls 4 enabled`
		Displays the status of the MPLS feature set.

Step 6	(Optional) **show feature | grep segment-routing**
	Example:
	`switch(config)# show feature | grep segment-routing`
	`segment-routing 1 enabled`
		Displays the status of MPLS segment routing.

Reserving Labels for MPLS Label Imposition

You can reserve the labels that are to be statically assigned. Dynamic label allocation is not supported.

Before you begin

Ensure that the MPLS segment routing feature is enabled.

Procedure

	Command or Action	Purpose

Step 1	**configure terminal**
	Example:
	`switch# configure terminal`
	`switch(config)#`
		Enters global configuration mode.

Step 2	[**no**] **mpls label range** *min-value max-value* [**static** *min-static-value max-static-value*]	Reserves a range of labels for static label assignment.

	Command or Action	Purpose
	Example: `switch(config)# mpls label range 17 99 static 100 10000`	The range for the minimum and maximum values is from 16 to 471804.
Step 3	(Optional) **show mpls label range** **Example:** `switch(config)# show mpls label range`	Displays the label range that is configured for static MPLS.
Step 4	(Optional) **copy running-config startup-config** **Example:** `switch(config)# copy running-config startup-config`	Copies the running configuration to the startup configuration.

Configuring MPLS Label Imposition

You can configure MPLS label imposition on the device.

Note The **feature mpls segment-routing** command cannot be enabled when the following commands are in use: **feature nv overlay**, **nv overlay evpn**, **feature vpc**, and **feature vn-segment-vlan-based**.

Before you begin

Ensure that the MPLS segment routing feature is enabled.

Set a static label range as follows: **mpls label range 16 16 static 17 50000**.

Procedure

	Command or Action	Purpose

Step 1	**configure terminal**
	Example:
	`switch# configure terminal`
	`switch(config)#`
		Enters global configuration mode.

Step 2	**interface** *type slot/port*
	Example:
	`switch(config)# interface ethernet 2/2`
	`switch(config-if)#`
		Enters the interface configuration mode for the specified interface.

Step 3	[**no**] **mpls ip forwarding** **Example:** `switch(config-if)# mpls ip forwarding`	Enables MPLS on the specified interface. The **no** form of this command disables MPLS on the specified interface.

	Command or Action	Purpose

Step 4	**mpls static configuration**
	Example:
	`switch(config-if)# mpls static configuration`
	`switch(config-mpls-static)#`
		Enters MPLS static global configuration mode.

Step 5	**address-family ipv4 unicast**
	Example:
	`switch(config-mpls-static)# address-family ipv4 unicast`
	`switch(config-mpls-static-af)#`
		Enters global address family configuration mode for the specified IPv4 address family.

Step 6	**lsp** *name*
	Example:
	`switch(config-mpls-static-af)# lsp lsp1`
	`switch(config-mpls-static-lsp)#`
		Specifies a name for LSP.

Step 7	**in-label** *value* **allocate policy** *prefix*
	Example:
	`switch(config-mpls-static-lsp)# in-label 8100 allocate policy 15.15.1.0/24`
	`switch(config-mpls-static-lsp-inlabel)#`
		Configures an in-label value and a prefix value (optional).

Step 8	**forward**
	Example:
	`switch(config-mpls-static-lsp-inlabel)# forward`
	`switch(config-mpls-static-lsp-inlabel-forw)#`
		Enters the forward mode.

Step 9	**path** *number* **next-hop** *ip-address* **out-label-stack** *label-id label-id* **Example:** `switch(config-mpls-static-lsp-inlabel-forw)# path 1 next-hop 13.13.13.13 out-label-stack 16 3000`	Specifies the path. The maximum number of supported paths is 32.
Step 10	(Optional) **copy running-config startup-config** **Example:** `switch(config-mpls-static-lsp-inlabel-forw)# copy running-config startup-config`	Copies the running configuration to the startup configuration.

What to do next

For information about displaying and clearing MPLS statistics for Segment Routing, see Displaying MPLS Statistics and Clearing MPLS Statistics.

Verifying the MPLS Label Imposition Configuration

To display the MPLS label imposition configuration, perform one of the following tasks:

Command	Purpose
show feature | grep segment-routing	Displays the status of MPLS label imposition.
show feature-set	Displays the status of the MPLS feature set.
show forwarding mpls label *label*	Displays MPLS label forwarding statistics for a particular label.
show mpls label range	Displays the label range that is configured for MPLS label imposition.
show mpls static binding {**all** | **ipv4**}	Displays the configured static prefix or label bindings.
show mpls switching [**detail**]	Displays MPLS label switching information.
show running-config mpls static	Displays the running static MPLS configuration.

This example shows sample output for the **show forwarding mpls label 8100** command:

```
slot 1
=======
--------+-----------+------------------+---------------+-------------+----------------------
Local|Prefix|FEC          |Next-Hop  |Interface | Out Label |Table Id |(Prefix/Tunnel
id)|Label
--------+-----------+------------------+---------------+-------------+----------------------
8100 |0x1   |25.25.0.0/16 |12.12.1.2 |Po121     |3131 SWAP  |         |                   |
 17
"    |0x1   |25.25.0.0/16 |12.12.2.2 |Eth1/51   |3131 SWAP  |         |                   |
 17
"    |0x1   |25.25.0.0/16 |12.12.3.2 |Vlan122   |3131 SWAP  |         |                   |
 17
"    |0x1   |25.25.0.0/16 |12.12.4.2 |Vlan123   |3131 SWAP  |         |                   |
 17
```

This example shows sample output for the **show mpls static binding all** command:

```
LI_TEST1 25.25.0.0/16: (vrf: default) Incoming label: 8100
LSP Type: POLICY
  Outgoing labels:
     (path 1)  12.12.1.2 3131,17
     (path 2)  12.12.2.2 3131,17
     (path 3)  12.12.3.2 3131,17
     (path 4)  12.12.4.2 3131,17

LI_TEST2 (vrf: default) Incoming label: 8200
LSP Type: XC
  Outgoing labels:
     (path 1)  12.12.3.2 3132,16
     (path 2)  12.12.4.2 3132,16
     (path 3)  12.12.1.2 3132,16
     (path 4)  12.12.2.2 3132,16
```

This example shows sample output for the **show mpls switching** command:

```
Legend:
(P)=Protected, (F)=FRR active, (*)=more labels in stack.

Local      Out-Label  FEC                                             Out-Interface
Next-Hop
8200       3132       Label 8200
12.12.3.2                                      *
8200       3132       Label 8200
12.12.4.2                                      *
8200       3132       Label 8200
12.12.1.2                                      *
8200       3132       Label 8200
12.12.2.2                                      *

Local      Out-Label  FEC                                             Out-Interface
Next-Hop
8100       3131       Pol 25.25.0.0/16
12.12.1.2                                      *
8100       3131       Pol 25.25.0.0/16
12.12.2.2                                      *
8100       3131       Pol 25.25.0.0/16
12.12.3.2                                      *
8100       3131       Pol 25.25.0.0/16
12.12.4.2                                      *
```

This example shows sample output for the **show running-config mpls static** command:

```
mpls static configuration
  address-family ipv4 unicast
    lsp LI_TEST2
      in-label 8100 allocate policy 25.25.0.0 255.255.0.0
        forward
          path 1 next-hop 12.12.1.2 out-label-stack 3131 17
          path 2 next-hop 12.12.2.2 out-label-stack 3131 17
          path 3 next-hop 12.12.3.2 out-label-stack 3131 17
          path 4 next-hop 12.12.4.2 out-label-stack 3131 17
```

This example shows sample output for the **show running-config mpls static all** command.

```
switch# show running-config mpls static all

!Command: show running-config mpls static all
!Time: Mon Aug 21 14:59:46 2017

version 7.0(3)I7(1)
logging level mpls static 5
mpls static configuration
address-family ipv4 unicast
lsp 9_label_stack_LPM
in-label 72000 allocate policy 71.200.11.0 255.255.255.0
forward
path 1 next-hop 27.1.32.4 out-label-stack 21901 29701 27401 24501 25801
lsp 9_label_stack_LPM_01
in-label 72001 allocate policy 72.201.1.1 255.255.255.255
lsp DRV-01
in-label 71011 allocate policy 71.111.21.0 255.255.255.0
forward
path 1 next-hop 27.1.31.4 out-label-stack implicit-null
lsp DRV-02
in-label 71012 allocate policy 71.111.22.0 255.255.255.0
forward
```

```
path 1 next-hop 8.8.8.8 out-label-stack 28901
lsp DRV-03
switch# show forwarding mpls label 72000

slot 1
=======

--------+-----------+------------------+----------------+-------------+-------
Local |Prefix |FEC |Next-Hop |Interface |Out
Label |Table Id |(Prefix/Tunnel id) | | |Label
--------+-----------+------------------+----------------+-------------+-------
72000 |0x1 |71.200.11.0/24 |27.1.32.4 |Eth1/21 |21901 SWAP
| | | | | 29701
| | | | | 27401
| | | | | 24501
| | | | | 25801
```

Configuration Examples for MPLS Label Imposition

This example shows how to configure MPLS label imposition by allocating a prefix and an incoming-label to out-label-stack binding:

```
switch(config-if)# mpls static configuration
switch(config-mpls-static)# address-family ipv4 unicast
switch(config-mpls-static-af)# lsp LI_TEST1
switch(config-mpls-static-lsp)# in-label 8100 allocate policy 25.25.0.0/16
switch(config-mpls-static-lsp-inlabel)# forward
switch(config-mpls-static-lsp-inlabel-forw)# path 1 next-hop 12.12.1.2 out-label-stack 3131
 17
switch(config-mpls-static-lsp-inlabel-forw)# path 2 next-hop 12.12.2.2 out-label-stack 3131
 17
switch(config-mpls-static-lsp-inlabel-forw)# path 3 next-hop 12.12.3.2 out-label-stack 3131
 17
switch(config-mpls-static-lsp-inlabel-forw)# path 4 next-hop 12.12.4.2 out-label-stack 3131
 17
```

To remove a next-hop, you can use

```
no path 1
```

To remove the named lsp, you can use

```
no lsp LI_TEST1
```

This example shows how to configure MPLS label imposition by allocating an incoming-label to out-label-stack binding (no prefix):

```
switch(config-if)# mpls static configuration
switch(config-mpls-static)# address-family ipv4 unicast
switch(config-mpls-static-af)# lsp LI_TEST1
switch(config-mpls-static-lsp)# in-label 8200 allocate
switch(config-mpls-static-lsp-inlabel)# forward
switch(config-mpls-static-lsp-inlabel-forw)# path 1 next-hop 12.12.3.2 out-label-stack 3132
 16
switch(config-mpls-static-lsp-inlabel-forw)# path 2 next-hop 12.12.4.2 out-label-stack 3132
 16
switch(config-mpls-static-lsp-inlabel-forw)# path 3 next-hop 12.12.1.2 out-label-stack 3132
 16
switch(config-mpls-static-lsp-inlabel-forw)# path 4 next-hop 12.12.2.2 out-label-stack 3132
```

```
16
```