

show crash

- show crash config, on page 1
- show crash list, on page 2
- show crash all, on page 2
- show crash number , on page 2

show crash config

This chapter includes the **show crash config** command output table.

Table 1: show crash config Command Output Descriptions

Field	Description
URL	Specifies the URL where cores are stored.
Disk Space Limit	Specifies the limit for the disk space. Displays "Not Configured" if the limit is not configured.
Rotate Core Files Limit	Specifies the limit for the rotate core files.
Core File Max-Size	Specifies the maximum size for the core file.
Core File Compression	Specifies the compression format of the core file.
Core Transmit Timeout	Specifies the timeout for core transmission.
Core Obfuscation	Specifies whether core obfuscation is enabled or disabled.
Async Core Transfer	Specifies whether async core transfer is enabled or disabled.
Mandatory VPP Core Transfer	Specifies whether mandatory VPP core transfer is enabled or disabled.
Critical Task	Specifies whether critical task is enabled or disabled.

show crash list

The following command shows list of all fatal crash records.

Table 2: show crash list Command Output Descriptions

Field	Description
Card	Serial number for the fatal crash records.
Time	The actaul time at which the fatal crash occurred.
Process	Shows the name of the Snapped Process.
Card/CPU/PID	Shows list of Card numbers, CPU complexity and PID numbers.
Harward Serial Number	Shows list of hardware serial numbers of the crashed records.

Use the following commands to view fatal crash records.

- `show crash list` **`clear crash list`** *`<no>`* `: Clears list of Fatal crash record.`
- `show crash number` **`clear crash number`** *`<no>`* `: Copies particular Fatal crash record to location.`

show crash all

The following command shows all fatal crash records.

Table 3: show crash all Command Output Descriptions

Field	Description
SW Version	Shows software version numbers of all fatal crash records.
Similar Crash Count	Shows all similar crash count numbers of fatal crash records.
Time of First Crash	Shows the actual time of the first fatal crash occurrence.

show crash number

The following command shows a particular Fatal crash record.

Table 4: show crash number Command Output Descriptions

Field	Description
SW Version	Shows the software version number of the fatal crash records.

Field	Description
Similar Crash Count	Shows the total count number of similar fatal crashes.
Time of First Crash	Shows the actual time of the first fatal crash record.