如何从档案mbox提取电子邮件注册电子邮件安全工具？

Contents

[Introduction](#)
[如何从档案mbox提取电子邮件注册ESA ？](#)
[Related Information](#)

Introduction

本文描述如何从电子邮件安全工具创建的归档日志提取电子邮件(ESA)。

如何从档案mbox提取电子邮件注册ESA ？

1. 检索您会提取电子邮件从的档案mbox日志。 如何检索档案mbox是可用的在提供的*条款*。 (https://www.cisco.com/c/en/us/support/docs/security/email-security-appliance/118315-technote-esa-00.html)
2. 使用文本编辑，打开归档文件。使用*Notepad++*，下面的示例显示。
3. 识别您希望提取在归档日志外面的电子邮件。每个电子邮件在档案从**从**<address>将开始。
4. 复制单个电子邮件的内容到一个新的文本文件并且保存它作为**.eml**扩展名。
5. 打开在您的邮件客户端的提取的电子邮件，例如Outlook查看内容。

Note: 档案mbox日志可能包含多个电子邮件。

示例在归档日志内的电子邮件来源：

```
From test1@cisco.com Mon Jan 15 08:31:54 2018
X-IronPort-RCPT-TO: test2@cisco.com
Authentication-Results: ironport.example.com; spf=None
smtp.pra=test1@cisco.com; spf=SoftFail smtp.mailfrom=test1
@cisco.com; spf=None smtp.helo=postmaster@LIBIVARG-6622F
Received-SPF: None (ironport.example.com: no sender authenticity
  information available from domain of test1@cisco.com)
  identity=pra; client-ip=10.196.112.18;
  receiver=ironport.example.com;
  envelope-from="test1@cisco.com"; x-sender="test1@cisco.com";
  x-conformance=sidf_compatible
Received-SPF: SoftFail (ironport.example.com: domain of
  test1@cisco.com is inclined to not designate 10.196.112.18 as
  permitted sender) identity=mailfrom; client-ip=10.196.112.18;
  receiver=ironport.example.com;
  envelope-from="test1@cisco.com"; x-sender="test1@cisco.com";
  x-conformance=sidf_compatible; x-record-type="v=spf1"
Received-SPF: None (ironport.example.com: no sender authenticity
  information available from domain of
  postmaster@LIBIVARG-6622F) identity=helo;
  client-ip=10.196.112.18; receiver=ironport.example.com;
  envelope-from="test1@cisco.com";
  x-sender="postmaster@LIBIVARG-6622F";
  x-conformance=sidf_compatible
Received: from unknown (HELO LIBIVARG-6622F) ([10.196.112.18])
  by ironport.example.com with ESMTP; 15 Jan 2018 08:31:54 +0530
MIME-Version: 1.0
From: test1@cisco.com
To: test2@cisco.com
Date: 15 Jan 2018 11:16:23 +0530
Subject: Test archive filter
Content-Type: multipart/mixed; boundary="--boundary_0_
05c6bfa8-119c-40df-b0e9-917b1ffc110e



----boundary_0_05c6bfa8-119c-40df-b0e9-917b1ffc110e
Content-Type: text/plain; charset=us-ascii
Content-Transfer-Encoding: quoted-printable

This is a test email. Please ignore. Or don't.
----boundary_0_05c6bfa8-119c-40df-b0e9-917b1ffc110e
Content-Type: application/octet-stream; name=Onward.pdf
Content-Transfer-Encoding: base64

Q29udGVudC1UeXBlOiBtdWx0aXBhcnQvcmVsYXRlZDsNCiBib3VuZGFyeT0iLS0tLT1
fTmV4
dFBhcnRfODcwOTcxMC40MzU4MjUxMDI2NTI1DQpYLUJlZzJNaW11OiBUcnVlDQpYLU1
zZzJN
aWIlUXNaWVudC17dWJtaXQtVG1tZTogTW9uLCAwOCBKYW4gMjAxOCAxNzoyMDowNSA
tMDUw
```



在Outlook提取和打开的示例电子邮件：



Related Information

- Cisco电子邮件安全工具-终端用户指南
- Technical Support & Documentation - Cisco Systems
- 什么是UNIX mbox (邮箱)格式？
- 日志在哪里如何存储在Cisco电子邮件安全工具(ESA)，并且访问他们？
- 如何归档在电子邮件安全工具(ESA)上的电子邮件